


5. Define logical volume ranges to the access groups, as shown in Figure I-15.



"" (#BA002): Add Access Group Range

Volume Range:


From: To:

Access Group:

▼

Figure I-15 Add VOLSER range for TEST LPAR

You can see that the ranges are assigned to their correct hosts, as shown in Figure I-16.



"" (#BA002): Library Port Access Groups

Last Refresh: Nov 9, 2012 10:14:49 AM

Access Groups:

-- Select Action --

Select	Name	Library Port IDs	Description
<input type="checkbox"/>	-----	0x01-0x10 0x21-0x30 0x41-0x50 0x61-0x70 0x81-0x90 0xA1-0xB0 0xC1-0xD0 0xE1-0xF0	-----
<input type="checkbox"/>	PROD	0x01-0x0E 0x41-0x4E	access group for PROD
<input type="checkbox"/>	TEST	0x0F-0x10 0x4F-0x50	access group TEST

Page 1 of 1 Page 1 of 1 Selected: 0 Total: 3 Shown: 3

Access Group Volume Ranges:

-- Select Action --

Select	Start Volser	End Volser	Access Group
<input type="radio"/>	A00000	A99999	PROD
<input type="radio"/>	B00000	B99999	TEST

Page 1 of 1 Page 1 of 1 Selected: 0 Total: 2 Shown: 2

Figure I-16 Summary of access groups and VOLSER ranges