

Figure 9-56 MI Virtual Volume Search entry window

A maximum of 10 search queries results or 2 GB of search data can be stored at one time. If either limit is reached, the user deletes one or more stored queries from the Previous Virtual Volume Searches window before creating a search.

To view the results of a previous search query, select **Previous Searches** to see a table that contains a list of previous queries. Click a query name to display a list of virtual volumes that match the search criteria.

To clear the list of saved queries, select the check box next to one or more queries to be removed, select **Clear** from the menu, and then, click **Go**. This operation does not clear a search query already in progress.

Confirm the decision to clear the query list. Select **OK** to clear the list of saved queries, or **Cancel** to retain the list of queries.

To create a search query, enter a name for the new query. Enter a value for any of the fields and select **Search** to start a new virtual volume search. The query name, criteria, start time, and end time are saved along with the search results.

To search for a specific VOLSER, enter parameters in the New Search Name and Volser fields and then, click **Search**.

When looking for the results of earlier searches, click **Previous Searches** in the Virtual Volume Search window (see Figure 9-56).